Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications



Open e-PRIOR elnvoicing Integration with PEPPOL

Technical specifications

DIGIT

Directorate-General for Informatics

ISA² Programme ec.europa.eu/isa2

DISCLAIMER

This document is for informational purposes only and the Commission cannot be held responsible for any use which may be made of the information contained therein. References to legal acts or documentation of the European Union (EU) cannot be perceived as amending legislation in force or other EU documentation.

The document contains a brief overview of technical nature and is not supplementing or amending terms and conditions of any procurement procedure; therefore, no compensation claim can be based of the contents of the present document.

The information and views set out in this publication are those of the author(s) and do not necessarily reflect the official opinion of the European Commission. The European Commission does not guarantee the accuracy of the data included in this document. Neither the European Commission nor any person acting on the European Commission's behalf may be held responsible for the use which may be made of the information contained therein

EUROPEAN COMMISSION

Directorate-General for Informatics

Directorate B- Interoperability Solutions for public administrations, businesses and citizens

Unit B6 — ISA² Programme

Contact: DIGIT EPROCUREMENT SUPPORT

E-mail: <u>DIGIT-EPROCUREMENT-SUPPORT@ec.europa.eu</u>

European Commission B-1049 Brussels

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

LEGAL NOTICE

EUROPE DIRECT is a service to help you find answers to your questions about the European Union

Freephone number (*): 00 800 6 7 8 9 10 11

(*) The information given is free, as are most calls (though some operators, phone boxes or hotels may charge you)

This document has been prepared for the European Commission however it reflects the views only of the authors, and the Commission cannot be held responsible for any use which may be made of the information contained therein.

More information on the European Union is available on the Internet (http://www.europa.eu).

Luxembourg: Publications Office of the European Union, 2014

Print	ISBN [number]	ISSN [number]	doi:[number]	[Catalogue number]
PDF	ISBN [number]	ISSN [number]	doi:[number]	[Catalogue number]
EPUB	ISBN [number]	ISSN [number]	doi:[number]	[Catalogue number]

© European Union, 2018

Reproduction is authorised provided the source is acknowledged.

PRINTED IN [COUNTRY]

PRINTED ON ELEMENTAL CHLORINE-FREE BLEACHED PAPER (ECF)

PRINTED ON TOTALLY CHLORINE-FREE BLEACHED PAPER (TCF)

PRINTED ON RECYCLED PAPER

PRINTED ON PROCESS CHLORINE-FREE RECYCLED PAPER (PCF)

Image(s) © DIGIT B4, 2018

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

DOCUMENT METADATA

Property	Value
Release date:	June 2018
Status:	Published in joinup
Authors:	George Vaicar (DIGIT B4), Grzegorz Gaudyn (DIGIT B4)
Keywords (to increase the SEO presence)	eProcurement, eInvoicing, PEPPOL, interoperability, e-PRIOR

The ISA² programme supports the development of digital solutions that enable public administrations, businesses and citizens in Europe to benefit from interoperable cross-border and cross-sector public services.

ISA² is running from **1 January 2016** until **31 December 2020**. The programme was <u>adopted</u> in November 2015 by the European Parliament and the Council of European Union.

Solutions developed by ISA² **and under its predecessor ISA** are generally available for **free** and can be found <u>here</u>.

Under the ISA² programme, the following **actions are supported:** <u>ISA² action overview</u> <u>page</u>.

EXECUTIVE SUMMARY

Short Abstract (150 words)	Underlying document describes the technical aspects of the joinup release of Open e-PRIOR v2.2.0 that includes a component for integrating with the PEPPOL network, and back office elnvoicing Viewer. It can be used by any public administration to build an elnvoicing solution interoperable with the PEPPOL network.
Objectives (150 words)	Provide technical guidance on the architecture, installation and usage scenarios of the platform.
Method (300 words)	This document offers an architectural overview, a step by step installation guide as well as information on how to configure the platform and how to test it. It also includes an extension point, presenting the two options available for connecting a customer elnvoicing back-office to the platform.
Conclusions (150 words)	Technical document about the Open e-PRIOR package developed under the ISA2 programme.

AUDIENCE

This document describes the technical aspects of the joinup release of Open e-PRIOR that includes a component for integrating with the PEPPOL network and the back office elnvoicing Viewer.

It provides an architectural overview, a step by step installation guide as well as information on how to configure the platform and how to test it.

It also includes an extension point, presenting the two options available for connecting a customer elnvoicing back-office to the platform.

This document is intended for the following audiences:

AUDIENCE	TARGETED IN THIS DOCUMENT
POLICY OFFICERS	
IT PROVIDERS	
SERVICE PROVIDERS	
IT ARCHITECTS	
COMM EXPERTS	
LEGAL OFFICERS	

TABLE OF CONTENTS

1	INTRO	DUCTION AND BUSINESS CONTEXT	6
2	PRESEN	TATION OF THE PEPPOL EDELIVERY NETWORK	9
	2.1 Овт/	INING A PEPPOL CERTIFICATE FOR THE ACCESSPOINT	9
3	HIGH L	EVEL ARCHITECTURE VIEW	. 11
	3.1 DEPL	DYMENT DIAGRAM	. 12
	3.2 Desc	RIPTION OF THE MODULES	. 13
	3.2.1	Oxalis Access Point	. 13
	3.2.2	e-TrustEx	. 13
	3.2.3	e-TrustEx Adapter	. 13
	3.2.4	e-IrustEx Web	. 14
	3.3 SEQU	ENCE DIAGRAM	. 15
4	INSTAL	LATION GUIDE	. 18
	4.1 Doc	ER INSTALLATION	. 18
	4.2 RUN	IING THE APPLICATION WITH DOCKER COMPOSE	. 19
	4.2.1	Updating the environment variables used by Docker	. 20
	4.2.2	Launching and shutting down the application	. 21
	4.3 PORT	S EXPOSED BY THE DOCKER CONTAINERS	. 22
	4.4 CON	IECTING TO THE DATABASE	. 23
	4.5 END	OINTS FOR ACCESSING THE APPLICATIONS OF THE PLATFORM	. 25
	4.6 SPEC	FIC SETTINGS WHEN RUNNING DOCKER I OOLBOX ON WINDOWS OR MAC	. 28
	4.7 EIRU	STEX WEB REQUIREMENTS	. 32
_			
5	CONFIG	URING THE PLATFORM	. 35
5	CONFIC	URING THE PLATFORM	. 35 . 35
5	CONFIC 5.1 USE 5.2 CREA	THE EXISTING DEFAULT CONFIGURATION	. 35 . 35 . 35
5	CONFIC 5.1 Use 5.2 Crea 5.3 Crea	URING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE	. 35 . 35 . 35 . 36
5 6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA SENDIN	GURING THE PLATFORM	. 35 . 35 . 35 . 36 . 36 . 38
5 6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 6.1 USIN	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT	. 35 . 35 . 35 . 36 . 36 . 38
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 6.1 USIN 6.1 USIN 6.1.1	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier	. 35 . 35 . 36 . 36 . 38 . 38 . 38
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 6.1 USIN 6.1.1 6.1.2	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer	. 35 . 35 . 36 . 36 . 38 . 38 . 38 . 38
6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT	. 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 38 . 40
6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.1 6.1.2 6.2 USIN 6.2.1	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate	. 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 40 . 41
6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 6.1 USIN 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2	GURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE I'G BUSINESS MESSAGES TO THE PLATFORM I'G THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier I'G THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT I'G THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Configuring the self-signed certificate with a valid PEPPOL certificate	.35 .35 .35 .36 .38 .38 .38 .38 .38 .40 .41 .41
6	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3	GURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE I'G BUSINESS MESSAGES TO THE PLATFORM I'G THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer I'G THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate Configuring the standalone client Sample business messages provided in the package	.35 .35 .35 .36 .38 .38 .38 .38 .38 .40 .41 .41
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4	GURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA SENDIN 6.1 USIN 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3 CHEC	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier. As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42 . 42
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3 CHEC 6.3.1	GURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX. Using the database	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42 . 42 . 42 . 43
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3 CHEC 6.3.1 6.3.2 6.4 DUID	BURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE I'G BUSINESS MESSAGES TO THE PLATFORM I'G BUSINESS MESSAGES TO THE PLATFORM I'G THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer I'G THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX. Using SoapUI Using SoapUI	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42 . 42 . 42 . 43 . 43
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 5.3 CREA 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3 CHEC 6.3.1 6.3.2 6.4 BUSI	BURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE I'G BUSINESS MESSAGES TO THE PLATFORM I'G BUSINESS MESSAGES TO THE PLATFORM I'G BUSINESS MESSAGES TO THE PLATFORM I'G THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer I'G THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX Using the database Using SoapUI Ness VALIDATION (SCHEMATRON)	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42 . 42 . 43 . 43 . 43
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA 6.1 USIN 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3.1 6.3.2 6.3.1 6.3.2 6.4 BUSI ANNEX	BURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX Using the database Using SoapUI MESS VALIDATION (SCHEMATRON) : CREATING A CUSTOMER E-INVOICING BACK-OFFICE	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 42 . 42 . 43 . 43 . 43 . 45
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA 5.3 CREA SENDIN 6.1 USIN 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3 CHEC 6.3.1 6.3.2 6.4 BUSI ANNEX 7.1 STOF	BURING THE PLATFORM I'HE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX. Using the database Using SoapUI MESS VALIDATION (SCHEMATRON) : CREATING A CUSTOMER E-INVOICING BACK-OFFICE E AND FORWARD MESSAGING PATTERN.	. 35 . 35 . 35 . 36 . 38 . 38 . 38 . 38 . 38 . 40 . 41 . 41 . 41 . 41 . 42 . 42 . 43 . 43 . 43 . 45
5	CONFIC 5.1 USE 5.2 CREA 5.3 CREA SENDIN 6.1 USIN 6.1.1 6.1.2 6.2 USIN 6.2.1 6.2.2 6.2.3 6.2.4 6.3.2 6.3.1 6.3.2 6.4 BUSI ANNEX 7.1 STOR 7.2 STOR	BURING THE PLATFORM THE EXISTING DEFAULT CONFIGURATION TE NEW CONFIGURATION USING THE CIPADMIN MODULE TE NEW CONFIGURATION FOR E-TRUSTEX WEB MODULE IG BUSINESS MESSAGES TO THE PLATFORM IG BUSINESS MESSAGES TO THE PLATFORM IG BUSINESS MESSAGES TO THE PLATFORM IG THE PROVIDED SOAPUI SAMPLE PROJECT As Supplier As Customer IG THE STANDALONE CLIENT THAT SIMULATES A SENDING OXALIS ACCESSPOINT Replacing the self-signed certificate with a valid PEPPOL certificate. Configuring the standalone client Sample business messages provided in the package Instructions on how to send messages to the Oxalis AccessPoint KING THE RESULT OF MESSAGE PROCESSING IN E-TRUSTEX. Using the database Using SoapUI NESS VALIDATION (SCHEMATRON) : CREATING A CUSTOMER E-INVOICING BACK-OFFICE E AND FORWARD MESSAGING PATTERN E AND COLLECT MESSAGING PATTERN	.35 .35 .35 .36 .38 .38 .38 .38 .38 .38 .40 .41 .41 .41 .41 .42 .42 .43 .43 .43 .43 .45 .46



Introduction and business

context

1 Introduction and business context

The Directive 2014/55/EU has enforced that any public administration in Europe shall accept electronic invoices respecting the European Norm by November 2019.

In order to help administrations to meet this goal and on basis of requests of some countries, Open e-Prior has built a release that incorporates a gateway to the PEPPOL network as a first step to alignment to the e-Invoicing European Norm.

This release would provide:

- either a transitional solution for administrations not yet prepared for the Directive
- and /or a back-up solution to access received invoices
- or a solution to test the reception of PEPPOL invoices.

This release does not include anymore a supplier portal as it relies directly on the gateway and on elnvoicing Viewer.



Presentation of the PEPPOL eDelivery network The following description comes from the PEPPOL website (http://peppol.eu):

PEPPOL uses the eDelivery Network to connect different eProcurement systems by establishing a set of common business processes and technical standards. This provides an interoperable and secure network connecting all Access Points using the same electronic messaging protocol and formats and applying digital signature technologies to secure message content.

Once connected to the PEPPOL eDelivery Network (via a PEPPOL Access Point), public agencies and private enterprises can quickly and easily reach any other trading partner, also using PEPPOL.

The PEPPOL eDelivery Network's architecture is depicted in the diagram below (from https://peppol.eu/what-is-peppol/peppol-transport-infrastructure/):





Source: https://peppol.eu/what-is-peppol/peppol-transport-infrastructure

The following Prezi presentation shows in more detail the components of the PEPPOL network, their role and how they interact. It also shows how the PEPPOL network interacts with the two components which are part of the current release: the PEPPOL-eTrustEx Adapter and e-TrustEx.

The presentation can be accessed here: <u>https://prezi.com/d92orvsm2bzy/view</u>

2 **<u>Presentation of the PEPPOL eDelivery network</u>**

2.1 Obtaining a PEPPOL certificate for the AccessPoint

The PEPPOL network uses a PKI to secure the communication between its network components.

Detailed information about the network specifications can be found on the PEPPOL website (https://peppol.eu/downloads/the-peppol-edelivery-network-specifications/)

The steps to be followed to obtain a PEPPOL certificate are also described on the PEPPOL website: https://peppol.eu/downloads/ap-guidelines/, in the step "How to enrol for OpenPEPPOL PKI certificates".

The guide includes info about how to import the new certificate into the keystore that will be referenced later in the chapters <u>4.2 Running the application with docker-compose</u> and <u>6.2.2 Configuring the standalone client</u>



High level architecture view

3 High level architecture view

The objective of this system is to allow the reception of UBL Invoices and Credit Notes sent by suppliers through the PEPPOL network and to send them to the customer via e-TrustEx.

More information about UBL documents is available in: <u>https://www.oasis-open.org/committees/ubl/</u>.

The following diagram provides a short description of the context:



Fig. 2. Architecture

A supplier sends via its PEPPOL Access Point an electronic document.

The Access Point transmits (using the AS2 protocol) the document to the Access Point included in this package, which is an instance of the Oxalis project (https://github.com/difi/oxalis) of the Norwegian Agency for Public Management and eGovernment.

The Adapter component in the above diagram retrieves the document and sends it to e-TrustEx that makes it available to the final recipient (the customer) via e-TrustEx Web.

3.1 Deployment diagram

The following diagram depicts the deployment model of the modules included in the current release:



Fig. 3. Deployment model

The modules of the system (Oxalis AccessPoint, e-TrustEx Adapter, e-TrustEx, e-TrustEx Web) are deployed as Docker containers based on customized Docker images.

Each of the four modules has its own DB schema configured inside the MySql Docker container.

More details about Docker can be found in the installation guide (chapter <u>4. Installation</u> <u>guide</u>).

Outside the Docker context, the system also includes a standalone client (java application) that is used to simulate another PEPPOL AccessPoint that sends messages to the Oxalis AccessPoint in the above diagram.

3.2 Description of the modules

The four modules composing this package are described below.

3.2.1 Oxalis Access Point

The AccessPoint is a component of the PEPPOL network. General documentation about PEPPOL AccessPoints can be found on the PEPPOL website in the area "Access Point (AP) Implementation Guidelines" (https://peppol.eu/downloads/ap-guidelines/).

The Oxalis AccessPoint component in the above diagram is a customisation of the Oxalis open-source project (https://github.com/difi/oxalis) developed by the Norwegian Agency for Public Management and eGovernment.

It is customized on the level of message persistence: it stores into the database the messages that it receives from the PEPPOL network whereas in the default implementation of the Oxalis AccessPoint it writes those messages to a file store.

3.2.2 e-TrustEx

e-TrustEx is an open-source platform developed under the ISA programme. It is offered to Public Administrations at European, national and regional level to set up secure exchanges of digital structured and unstructured documents from system to system via standardised interfaces.

Complete details about the e-TrustEx platform can be found on the joinup page <u>https://joinup.ec.europa.eu/software/openetrustex/description</u>. The version used in this package is 'Open e-TrustEx 2.3.0' (https://joinup.ec.europa.eu/node/161366).

e-TrustEx supports different policy domains but in the context of the current document we are only using the e-Procurement domain. The services exposed by e-TrustEx are SOAP-based web services and the XML exchanged as payload respects the UBL syntax (https://www.oasis-open.org/committees/ubl/).

3.2.3 e-TrustEx Adapter

As its name suggests, this component plays the role of adapter between the message format exchanged in the PEPPOL network and the one supported by e-TrustEx.

Both platforms (PEPPOL and e-TrustEx) use the UBL syntax for the XML messages exchanged, but the difference lies in how the message is constructed.

In the PEPPOL world, the business message (Invoice or CreditNote) contains the attached documents embedded (as base64 content) into the XML.

e-TrustEx exposes separate services for the business documents (SubmitInvoice, SubmitCreditNote) and for the AttachedDocuments (SubmitAttachedDocument).

Therefore the Adapter processes the incoming message received from PEPPOL, it extracts any potential attached document embedded into it and calls the dedicated services exposed by e-TrustEx for the Invoice/CreditNote and the AttachedDocuments.

After the Invoice/CreditNote is stored e-TrustEx, its human-readable representation (PDF format) of the XML is generated asynchronously. Later the Adapter calls the SubmitViewRequest web service to retrieve the human-readable PDF from e-TrustEx, this service returns the base64 representation of the PDF.

The DocumentWrapper concept in e-TrustEx represents a document that will be part of a Document Bundle. The Adapter calls the StoreDocumentWrapper service in e-TrustEx for each of the following documents:

- XML of the Invoice/CreditNote
- human-readable PDF produced by e-TrustEx for the Invoice/CreditNote (as described above, the PDF is obtained by calling the SubmitViewRequest service)
- any document attached to the Invoice/CreditNote.

In the next step the Bundle XML, which contains metadata (DocumentWrapper ID, type, file name, size, hash method and hash) about all the DocumentWrappers, is built. Later on, this is used as payload of the SubmitDocumentBundle service.

Once created in the e-TrustEx database, the Bundle is routed to the e-TrustEx Web component to display its content to the receiver user, the Customer.

The current implementation of the Adapter assumes that the Sender and Receiver of the PEPPOL message are already configured in e-TrustEx, as well interchange agreements to send Invoice/CreditNote, AttachedDocument, DocumentWrapper and Bundle. More details about the configuration of the platform can be found in chapter <u>5. Configuring the platform</u>.

If the Sender/Receiver does not exist in e-TrustEx, the message will remain in a 'pending' state in the Adapter's database allowing it to be reprocessed after the necessary configuration has been done in e-TrustEx with the CIPAdmin tool (defined in <u>5.2 Create</u> <u>new configuration using the CIPAdmin module)</u>.

3.2.4 e-TrustEx Web

e-TrustEx Web is an open-source module developed under the ISA programme. It is offered to Public Administrations at a European, national and regional level to view in a secure way the documents stored in e-TrustEx.

In the context of the current document e-TrustEx Web is configured with basic functionality to browse Invoices/CreditNotes by their recipient (see document "<u>elnvoicing</u> <u>Viewer_Integration with PEPPOL - Quick User Guide</u>").

3.3 Sequence diagram



The following sequence diagram provides a description of how the components interact.

Fig. 4. Sequence diagram

When a Supplier sends a message through the PEPPOL network he uses his AS2 gateway that sends the message to the Oxalis AccessPoint instance. The AccessPoint saves the message in its database.

The new incoming messages are detected by the e-TrustEx Adapter component and a new workflow instance is started for each incoming message. The workflow is implemented using the Activiti BPMN workflow engine.

Activiti does the orchestration and calls different services to:

- retrieve and validate the message from the AccessPoint,
- resolve the Sender/Receiver parties,
- extract embedded attachments,
- send Invoice/CreditNote or Attached Document to e-TrustEx using web service calls,

- retrieve the Invoice/CreditNote human-readable PDF from e-TrustEx,
- store document wrappers of the Invoice/CreditNote XML and PDF, and any attached document sent by the Supplier together with the Invoice/CreditNote ,
- build the Bundle and send it to e-TrustEx using web service calls.

e-TrustEx stores the documents, the Bundles are routed to the e-TrustEx Web component to display its content to the receiver user (=the Customer) and eventually e-TrustEx notifies (push mechanism) the Customer that the documents are available or lets the Customer retrieve (pull mechanism) them as represented in the diagram.

More details about the two mechanisms can be found in chapter <u>7. Creating a Customer</u> <u>*e-Invoicing back-office*</u>.



Installation guide

4 Installation guide

The platform uses Docker (https://www.docker.com/) for building and releasing the package that contains the Oxalis AccessPoint, the Adapter, e-TrustEx and e-TrustEx Web. It uses custom Docker images based on Tomcat, MySql 5.6 and WildFly 10.1.0.

The three images are preconfigured, meaning that at runtime:

- the MySql container contains the data model of the four applications
- the Tomcat container is preconfigured and runs the Oxalis AccessPoint application
- the WildFly container is also preconfigured (data sources, JMS queues, ...) and the Adapter, e-TrustEx and e-TrustEx Web applications are deployed on it.

Both Tomcat and WildFly containers are linked at startup with the MySql container, in order for the applications to access the database.

The images are pushed as Public images on docker hub (https://docs.docker.com/toolbox/toolbox_install_windows/).

The installation environment includes a Docker engine that is Unix based and possibly Unix as the operation sytem therefore the commends are case sensitive.

4.1 Dock	er installation #ram/tostbo/toobor.instal.windows/ exemt: Regime © «SubmissionSPOC © FOLD © Weeks/PM © +Submission glasse: 🎐 BOX 💿 pre 🖉 PC-+Submission?- 📑 XOS
https://weather.com/fr-BE/temps/10jours//BI	00005188 De docs Guides Product manuals Glossary Reference Samples
Set Docker +	Install Docker Toolbox on Windows
Docker CE 👻	Legacy desktop solution. Docker Toolbox is for older Mac and Windows systems that do not meet the requirements of Docker for Mac and Docker for Windows. We recommend updating to the newer applications, if possible.
Cloud - Linux - MacOS	- Estimated reading site: 10 minutes Docker Toolibox provides a way to use Docker on Windows systems that do not meet minimal system requirements for the Docker for Windows app.
Microsoft Windows Docker CE Edge releases Docker Toolbox (legecy)	If you have not done so already, download the installer here: Get Docker Toolbox for Windows
Toolbas overview Install Toolbas on Mac Install Toolbas on Windows Kitematic • Troubleshooting Release notes	What you get and how it works Docker Toolbox includes the following Docker tools: Docker Cu client for running Docker Engine to create images and containers Docker Kachine soy ou can run Docker Engine commands from Windows terminals Docker Compose for running the <u>acker-compose</u> command Kitematic: the Docker Cull the Docker QuickSarts thell preconfigured for a Docker command-line environment Create WW tirtualBox
Docker EE Compatibility between Docker versions et started evelop with Docker	Because the Docker Engine daemon uses Linux-specific kernel features, you can't run Docker Engine natively on Windows. Instead, you must use the Docker Machine command. <u>docker-wachine</u> . to create and attach to a small Linux VM on your machine. This VM hosts Docker Engine for you on your Windows system. Tip: One of the advantages of the newer Docker for Windows solution is that it uses native virtualization and does not require VirtualBox to run Docker.
Configure networking	Step 1: Check your version
4 npp.7.5.9.Installer.exe ^ 🖬	

Fig. 5. Docker Installation

Docker (and Docker Compose) should be installed according to the operating system used. After installation, run "*docker-compose version*" at the Docker command line to verify if Docker Compose is installed.

On specific Windows versions (eg: Windows 7 Enterprise), only Docker Toolbox can be installed.

If used behind a proxy, the following proxy settings should be written at the beginning of the file start.sh (found in the installation folder of Docker Toolbox):

- PROXY_USER=<XXX>
- PROXY_PASS=<XXX>
- PROXY_SERVER=<XXX>
- PROXY_PORT=<XXX>
- export
 http_proxy=http://\${PROXY_USER}:\${PROXY_PASS}@\${PROXY_SERVER}:\${PROXY_POR
 T}/ export https_proxy=\${http_proxy}
- export HTTP_PROXY=\${http_proxy}
- export HTTPS_PROXY=\${http_proxy}

4.2 Running the application with Docker Compose

Compose is a tool for defining and running multi-container Docker applications (<u>https://docs.docker.com/compose/</u>).

It allows orchestrating different Docker containers and setting dependencies between them.

Assuming Docker Compose is installed, the following two files should be created in a local folder:

• <u>docker-compose.yml</u> with the following content:

mysql-peppol-viewer:

environment:

MYSQL_ROOT_PASSWORD: peppol

image: digiteprocurement/mysql-peppol-viewer

ports:

- "3306:3306"

volumes:

- \$MYSQL_DATA_VOLUME_PATH:/var/lib/mysql

wildfly-peppol-viewer:

links:

- mysql-peppol-viewer

ports:

- "8080:8080"

- "9990:9990"

command: ["./wait-for-it.sh", "mysql-peppol-viewer:3306", "--", "/opt/jboss/wildfly/bin/standalone.sh", "-c", "standalone-custom.xml", "-b", "0.0.0.0", "bmanagement", "0.0.0.0"]

image: digiteprocurement/wildfly-peppol-viewer

volumes:

- \$WILDFLY_PATH:/opt/jboss/wildfly/standalone/data

tomcat-peppol-viewer:

environment:

OXALIS_HOME: /usr/local/tomcat/.oxalis/

links:

- mysql-peppol-viewer

ports:

- "8081:8080"

- "443:443"

image: digiteprocurement/tomcat-peppol-viewer

volumes:

- \$OXALIS_KEYSTORE_PATH:/usr/local/tomcat/.oxalis/keystore

• .<u>env</u> with the following content:

MYSQL_DATA_VOLUME_PATH=/C/Users/USERNAME/mysql-docker-volume OXALIS_KEYSTORE_PATH=C:/Users/USERNAME/oxalis-keystore WILDFLY_PATH=C:/Users/USERNAME/docker/wildfly-docker-volume

4.2.1 Updating the environment variables used by Docker

Create the folders

• /C/Users/USERNAME/mysql-docker-volume

- c:/Users/USERNAME/oxalis-keystore
- c:/Users/USERNAME/docker/wildfly-docker-volume

The above ".env" file should be edited to specify the real path on the local host for the two environment variables:

- MYSQL_DATA_VOLUME_PATH specifies the folder where the MySql Docker container should store the data on the local host of the user
- OXALIS_KEYSTORE_PATH specifies the folder on the local host of the user where the keystore containing the real PEPPOL certificate has been stored (see chapter <u>2.1 Obtaining a PEPPOL certificate for the AccessPoint</u>). This variable is used by the Tomcat container that runs the Oxalis AccessPoint.
- WILDFLY_PATH specifies the folder where the WildFly Docker container should store the data from e-TrustEx (FILE_STORE_PATH parameter from etrustex.ETR_TB_METADATA table) on the local host of the user

If you are using Docker Machine on Mac or Windows, your Docker Engine daemon has only limited access to your macOS or Windows filesystem. Docker Machine tries to auto-share your /Users (macOS) or C:\Users (Windows) directory. More details here:

https://docs.docker.com/engine/tutorials/dockervolumes/#mount-a-host-directory-as-a-data-volume

Therefore it is advisable that the two environment variables should point to folders defined under /Users (for macOS) or C:\Users (for Windows).

4.2.2 Launching and shutting down the application

To **launch** the application:



Fig. 6. Docker Quickstart Terminal icon on the Windows pulpit

1. From the docker command line (Docker Terminal) navigate to the folder where the above files (docker-compose.yml and .env) have been saved.

2. Once there, run the following command: "docker-compose up -d".



Fig. 7. Docker Terminal

To **shut down** the containers:

1. Run "docker-compose stop && docker-compose rm -f"

Remark: Modify specific settings required for your environment that are described in the chapter **<u>4.6 Specific settings when running Docker Toolbox on Windows or Mac</u>**.

4.3 Ports exposed by the Docker containers

- The MySql Docker image exposes the port 3306.
- The WildFly Docker image exposes the ports 8080 and 9990.

• The Tomcat Docker image exposes the port 8081.

4.4 Connecting to the database

A DB client application (like DbVisualizer) can be used to connect to the MySql Docker container with the following connection parameters:

Download the latest DbVisualizer x +					
Download the latest DbVisualizer version - For Windows, macOS, Linux w.dbvis.com/download/10.0					
📱 The Weather Chann 📙 WIKIS 🎦 abacassets - Revision 🌒 e_SubmissionSPOC 📓 FOLIO WeeklyPM 🔳	e-Submission glossar 🔗 BC	DXI 📃 prvt 📷 PIC- e-Submission? ·	JOBS		
	Download Cust			Buy Pro Versi	on Q
Try out DbVisualizer Pro for 21 days Start the trial by running the latest version and then open the Evaluate Pro Edition under the Help menu.	Select version	on rsion: 10.0.15 2018-10-04	v		
DbVisualizer 10.0 What's New in 10.0 Release Notes 10.0.x Download 10.0.15 Users Guide: HTML PDF	10.0.15	s - released at 2.	018-10-04	. y Dov	vnload
	An installer	5	Installer Type	Download	With Java VM
Tested with		Windows 64-bit	ZIP	Download	Download
OS Support: Windows 10/8/7 Linux		Windows 32-bit	Setup ZIP	Download Download	Download
macOS 10.7.3+ Java 8 is required	é	macOS	Setup TGZ	Download Download	Download
Known Java issues for Windows, Linux, macOS users	۵	Linux	Setup DEB RPM	Download Download Download	
	UNIX	Unix	Setup TAR.GZ	Download Download	
📷 dbvis windows-x6exe 🔿 📵 dbvis windows-x6exe 🔿					

Fig. 8.

DbVisulaliser

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

S DbVisualizer Free 10.0.15						
File Edit View Database SQL Commander Tools Window Help						
DbVisualizer Fr	re					
🗘 📕 🖼 💢 🗔 🕣 🔰 🕺 式 New Co	nnection Wizard	the extended DbVisualizer Pro				
Connections						
Sele	ct Database Driver					
	V MySQL V					
	Select the appropriate database driver from the list above.					
		•				
G	< Back Next > Cancel					
- Instancio	ense key for Duvisualizer Pro					
Select To	ols->Connection Wizard menu choice to create a database connection					
2 Latest ne	vs, documentation and FAQs are available at http://www.dbvis.com					
		55M of 512M				

Fig. 9. Configuring a new database connection properties

- URL of the database server: *localhost* (or the IP from chapter <u>4.5 Specific settings</u> <u>when running Docker Toolbox on Windows or Mac</u>)

- port: 3306
- database: *peppol_adapter*
- user: root
- password: peppol

😂 DbVisualizer Free 10.0.15 - PEPPOL			
File Edit View Database SO	Commander Tools Window	Help	
1 <mark></mark>			
📕 Databases 📕 Scr 🖉 🕨 🖽	PEPPOL ×		
dal 🗖 📥 💓 📼		9599.01	Actions -
QP ■ ■ X □ •	Database Connecti	on: PEPPOL	Piccions V
Connections	PEPPOL		
E- D PEPPOL	Connection 📌 Propert	es	
	- Connection		
	Name	PEDDO	
	Notes		
	Database		
	Settings Format	Server Info	
	Database Type	Auto Detect (MySQL)	
	Driver (JDBC)	S MySQL	
	Database Server	192.168.99.100	
	Database Port	3306	
	Database	peppol_adapter	
	Authentication		
	Database Userid	root	
	Database Password	•••••	
	Options		
	Save Database Password	Sava Bahwaan Serrions	
	Permission Mode	Development	
	Buffer All Rows for a Result	m	
		Connect Disconnect Ping Server	
	Connection Message		
	An error occurred while esta	blishing the connection:	
	rai ciror occurred while esta	ononing are connection.	Â
	Long Message:		E
	communications link failure		
	The last packet sent success	sfully to the server was 0 milliseconds ago. The driver has not received any packets from the serv	/er. 🕌
		5 O Ø 65M	l of 512M

Fig. 10. Database connection properties

4.5 Endpoints for accessing the applications of the platform

After the previous step is done, the applications should be up and running. For the first execution of the platform, it may take few minutes to complete the MySql container initialization. The DDL and DML scripts embedded in the Docker image are executed only at the first run with docker-compose. Subsequent executions will use the data saved by the MySql Docker container in the location specified above (the MYSQL_DATA_VOLUME_PATH, WILDFLY_PATH environment variable).

When the containers have finished initialization, the following URLs are available:

 http://localhost:9990/console is the admin console of the WildFly 10 application server.

Login with user/password peppol/peppol.

Once connected, navigate to the Deployments tab and the three applications (etrustex.ear, etrustex-peppol-adapter.war and etx-wacc-modules-ear-wildfly.ear) should be "enabled" as in the screenshot below:

WildFly	Messages: 0 🛔 peppol 🗸
Home Deployments Configuration Runtime Access Control Patching	
Deployment Xdd Q etrustex-peppol-adapter.war etrustex-peppol-adapter.war Deployment is enabled Details Last enabled at 2017-04-27 08:31:57,073 UTC The deployment was never disabled Runtime name: etrustex-peppol-adapter.war	

Fig. 11. WildFly admin console

 http://localhost:8080/etrustex is the probing URL of e-TrustEx It shows the version number and the build date.



Fig. 12. Open_eTrustex version & Build date

• http://localhost:8080/etrustex-admin-web/ is the CIPAdmin configuration tool.

Login with user/password testadm/testadm.

This module allows the technical configuration of the platform (Suppliers and Customers exchanging business documents). More details about this tool can be found in chapter **5.2 Create new configuration using the CIPAdmin module**

	() cipadmin.logout
CIPAdmin	Welcome, testadm. Role General Administrator for : eProcurement *
Home Business Configuration \sim Technical Configuration \sim Monitoring and Support \sim	
Home	
As a General Administrator, you can configure parties and interchange agreements. Below you will	find a description of the configurations you can do.
Interchange Agreement Configuration residum re	
and more	

Fig. 13. CIPAdmin console

• http://localhost:8080/ e-trustex/ is the e-TrustEx Web, a user interface that plays the role of a basic back-office system, allowing the Customer to see the business document sent by the Supplier.

Login with user/password admin-web/admin-web.

More details about this tool can be found in chapter <u>5.3 Create new</u> configuration for the e-TrustEx Web module

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

🔶 🕞 🛐 http://192.1	58.99.100:8080/e-trustex/inbox.do	5 - Q	lidFly Management	🚞 Com
File Edit View Favor	ites Tools Help			
🚖 🍭 PM meetings 🚺	CED search リ APEX 🔻 リ DIGIT 👻 餐 AA Ord	er 🧧 ABAC rights 📰 ABA	C WF 🧧 SP - PROD 📌 BOXI 🧯	🗿 CP 🧧 DIA
e-TrustEx web-site is	using cookies. Cookies help us improv	ving the user experien	ce while using the web-si	te OK
	eTrustEx - Web	access		
European Commission	Trusted Exchange Pla	atform		
EUROPA > European Comm	imission > eTrustEx			
Messages	🤷 New 😷 Refresh Subject		Q	
	Inbox			
Inbox	All Unread			
Sent Sent				
Draft				

Fig. 14. E-Trustex Web

• http://localhost:8080/etrustex-peppol-adapter/login is the eTrustEx Adapter Administration Console.

Login with user/pwd as2admin/as2admin.

Inttp://192.168.99.100:8080/etrustex	-peppol-adapter/ap	p/main		0 - C	🧠 WildFly Manage	ement	🗯 Cor
File Edit View Favorites Tools Help							
🖕 🌒 PM meetings 🛄 CED search 퉬 APEX	🕶 퉬 digit 👻 🦉	AA Order	ABAC right	s 🚞 ABAC	: WF 🧃 SP - PROD	🥜 BOXI	🥘 CP 🥚 DI
	AS2 - e-Trust	Ex Adapt	ter Adminis	stration (Console		
Т	asks list	esh					
	Name						
F	Process instance						
	Creation Date			14			
	Error description						

Fig. 15. E-Trustex Adapter

• http://localhost:8081/manager/html is the admin console of Tomcat.

Login with user/password manager/manager.

It shows the status of the applications deployed and if successfully started, in the Applications table you should see the Path "/oxalis" with the status 'true' in the Running column.

							APACHE SOTWARE FOUNDATION
			Tomcat Wel	b Applicatior	n Manager		
Message:	K						
Hanagar							
List Applications			HTML Manager Help			Manager Help	Server Status
		1					
Applications							
Path	Version		Display Name	Running	Sessions	Commands	
1	None specified	Welcome to Tomcat		true	0	Start Stop Reload Undeploy	
2	None operation	There of the to Forme at	rendere to rombat		*	Expire sessions with idle ≥ 30 minutes	
(doce	None energified	Tome at Decumentation		taio	0	Start Stop Reload Undeploy	
(100.3	Inone specified	Tome at Doc unteritation	Tomcat Documentation		¥	Expire sessions with idle ≥ 30 minutes	
lessed as	New years and					Start Stop Reload Undeploy	
/examples	None specified	Serviet and JSP Examples		true	2	Expire sessions with idle ≥ 30 minutes	
				Start Stop Reload Undeploy			
(host-manager	None specified	Tomcat Host Manager Application		true	2	Expire sessions with idle ≥ 30 minutes	
		-				Start Stop Reload Undeploy	
(manager	None specified	Tomcat Manager Application	iomcat Manager Application		1	Expire sessions with idle ≥ 30 minutes	
levelie	New and Fed	auglio.		te un		Start Stop Reload Undeploy	
(GRAILS	Indrie apecilied	oxans		true	2	Expire sessions with idle ≥ 30 minutes	

Fig. 16. Tomcat admin console

 http://localhost:8081/oxalis/as2 is the probing URL of the Oxalis AccessPoint running on Tomcat.

It should return the message "Hello AS2 world" as below



4.6 Specific settings when running Docker Toolbox on Windows or Mac

At the time of writing this guide, Docker Toolbox is the only option available for using Docker on specific versions of Windows and Mac. The Toolbox installs Docker Client, Machine, Compose and Kitematic.

The following adaptations are needed for this particular configuration (be sure that the application is lunched with the command "docker-compose up -d"):

- 'localhost' in the URLs mentioned in the previous chapter (<u>3.4 Endpoints for</u> <u>accessing the applications of the platform</u>) should be replaced with the IP returned by the following docker command: "docker-machine ip default". In the default Docker Toolbox configuration, the IP returned is 192.168.99.100.
- the following sql statement should be run to update in the metadata table (OXA_ADAPTER_METADATA) the URL for calling the e-TrustEx web services (to replace 'localhost' with the IP returned by the previous step):
 - update peppol_adapter.OXA_ADAPTER_METADATA set MD_VALUE = 'http://192.168.99.100:8080/eprior/services/' where md_type = 'as2adapter_etrustex_endpoint';
 - update peppol_adapter.OXA_ADAPTER_METADATA set MD_VALUE = 'http://192.168.99.100:8080/etrustex/wrapperservices' where md_type = 'URL_STORE_BINARY_WEBSERIVCE';
 - update peppol_adapter.OXA_ADAPTER_METADATA set MD_VALUE = 'http://192.168.99.100:8080/etrustex/services' where md_type = 'URL_VIEW_WEBSERIVCE';
 - update peppol_adapter.OXA_ADAPTER_METADATA set MD_VALUE = 'http://192.168.99.100:8080/etrustex/services' where md_type = 'URL_BUNDLE_WEBSERIVCE';

😒 DbVisualizer Free 10.0.15 - Untitleo	d"
File Edit View Database SQL	L Commander Tools Window Help
📒 🖶 🖻 🗣 🖷 🗮 🛠 🖼	l 💇 🖡
📕 Databases 🧾 Scr 4 🕨 🗉	PEPPOL: peppol_adapter x > 1: Untitled* x
¢ 🗏 🔤 💢 🗔 -	▶ ▶ ▶ ● ● ● ★ ◎ ■ < > ☆ - ■ □ ■
Connections	Database Connection Sticky Database Schema
🖶 🛃 PEPPOL	▶ PEPPOL
🕀 🗧 activiti	1 update peppol_adapter.OXA_ADAPTER_METADATA set ND_VALUE = 'http://192.168.99.100:8080/eprior/services/' where md_type = 'as2adapter_etrustex_endpoint';
etrustex	2 update peppol_adapter.0X1_ADAPTER_NETADATA set ND_VALUE = 'http://192.168.99.100:8080/etrustex/wrapperservices' where md_type = 'URL_STORE_BINARY_WEBSERIVCE';
etxweb	suppare peppol_adapter.OxA_AUAPTEK_METAUATA SET NU_VALUE = "http://192.108.99.1000:0000/etrusteX/services" where md_type = 'UNL_VIEW_MEDSERVICE'
mysal	5
peppol adapter (Defaul	
LOCAL TEMPORARY	
SYSTEM TABLE	
SYSTEM VIEW	
B- TABLE	
I VIEW	
Procedures	
	н
	4:146 [601] INS
	Time Status Command Exec Fetch Rows Message SQL/Command

Fig. 18. Peppol – Peppol_Adapter

- the following sql statement should be run to update the URL for calling the e-TrustEx web services (to replace 'localhost' with the IP returned by the previous step) in the metadata table (ETX_WEB_CONFIG):
 - update etxweb.ETX_WEB_CONFIG set CFG_PROP_VALUE = 'http://192.168.99.100:8080/etrustex/services/DocumentWrapper-2.0' where CFG_PROP_NAME = 'etrustex.doc.wrapper.service.uri';

- update etxweb.ETX_WEB_CONFIG set CFG_PROP_VALUE = 'http://192.168.99.100:8080/etrustex/services/DocumentBundle-2.0' where CFG_PROP_NAME = 'etrustex.doc.bundle.service.uri';
- update etxweb.ETX_WEB_CONFIG set CFG_PROP_VALUE = 'http://192.168.99.100:8080/etrustex/services/RetrieveInterchangeAgreemen tsRequest-2.0' where CFG_PROP_NAME = 'etrustex.doc.agreement.service.uri';
- update etxweb.ETX_WEB_CONFIG set CFG_PROP_VALUE = 'http://192.168.99.100:8080/etrustex/services/RetrieveRequest-2.0' where CFG_PROP_NAME = 'etx.node.services.RetrieveRequestService.uri';
- update etxweb.ETX_WEB_CONFIG set CFG_PROP_VALUE = 'http://192.168.99.100:8080/etrustex/services/ApplicationResponse-2.0' where CFG_PROP_NAME = 'etx.node.services.application.response.url';



Fig. 19. Update etxweb.ETX_WEB_CONFIG

- the following sql statement should be run to update the URL for calling the e-TrustEx Web web services (to replace 'localhost' with the IP returned by the previous step) in the table (ETR_TB_ENDPOINT_WS):
 - update etrustex.ETR_TB_ENDPOINT_WS SET edp_ws_url='http://192.168.99.100:8080/etrustex/integration/services/node/DocumentBundleService/v2.0' WHERE id='1';
 - update etrustex.ETR_TB_ENDPOINT_WS SET edp_ws_url='http://192.168.99.100:8080/e-TrustEx/integration/services/node /ApplicationResponseService/v2.0' WHERE id='2';

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

DbVisualizer Free 10.0.15 - Untitle	ed"				0
File Edit View Database SQ	QL Commander Tools Window Help				
	19 b				
Databases Scr 4 + 0	PEPPOL: peppol_adapter x > 1: Untitled* x				
		1 1			
Connections	Database Connection	Sticky Database	Schema	Max Rows	Max C
- B PEPPOL	PEPPOL	💌 📕 etrustex		- 1000	-1
mysql peppol_adapter (Defau local TEMPORARY	a -				
mysql mysql CoEau CoEau System TABL System TABL System TABL VIEW TABLE VIEW G Procedures performance_schema	a 11) ms			Auto Commit: Off (0/0) (cp	1252 U
Improved adapter (Defau Eucola adapter (Defau Eucola adapter (Defau SYSTEN TABLE SYSTEN TABLE SYSTEN TABLE VEW TABLE VEW Procedures Procedures performance_schema	all) ms 			Auto Commit: Off (0/0) (\$1	1252 U
Imysql mysql IocAL TEHPORARY SYSTEH VALE SYSTEH VALE SYSTEH VALE SYSTEH VALE SYSTEH VALE SYSTEH VALE TAAL TAAL VEW YEW performance_schema	a 3.1 [1] INS ↓ tog ↓ to	Rows Hexage	SQL/Command	Auto Commit: Off (0/0) (54	1252 U
COAL THROWARD COAL THROWARD COAL THROWARD STITH VIEW STITH VIEW ALE COAL THROWARD COAL COAL	In [1] (INS) Union We will be a status Command Lose fetch for Three Status Command Lose fetch for y 116230 STARTIO	Rows Hessage Executing for: "PPPO"," [19-52]. Database: etwatex	SQL/Command	Auto Cammit: Off (8/95) [Cp1	1252 U
wyoł (Colar) wyoł (Colar) wyoł (Colar) construction (C	a a 11 [1] mms 	Row Hessape Executing for: YPPPOL' [PsySQL]. Database: etrustex 1 0 00		Auto Cammit: Off (0/0) Cp1 der_integration/services/code/DocumentBandleScrevice/v2.6/ WHI Bill der_integration/services/code/DocumentBandleScrevice/v2.6/ WHI Bill	1252 Ur ='1'

Fig. 20. Update etrustex.ETR_TB_ENDPOINT_WS SET edp_ws_url

the default capacity settings (CPU/RAM) of the docker machine 'default' should be changed in the Oracle VM VirtualBox Manager GUI and the following steps should be followed:

1. First stop the VM from the command line (Docker Quickstart Terminal): run "docker-machine stop".



Fig. 21. Run "docker-machine stop"

2. In Oracle VM VirtualBox Manager, go to Settings->System and change to at least 2 CPUs and 2048 RAM.



Fig. 22. Oracle VM VirtualBox icon

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

Oracle VM VirtualBox Ma File Machine Help	ger	
New Setting Decard 1	General System System Motherboard Processor Acceleration Display Base Memory: 4096 MB Storage 4 MB 4096 MB Audio Boot Order: Image: Optical Base Network Image: Optical Base 1mage: Optical Base Network Chipset: FILG Image: Optical Base 1mage: Optical Base V USB Pointing Device: Image: Sp: ZMouse Image: Optical Base Shared Folders Image: Optical Base Image: Optical Base Image: User Interface Image: Optical Base Image: Optical Base	
	Invalid settings detected 🕅 🕎 OK Cancel	
	Controller: 104 ACS7	



🍪 def	ault - Settings	? 🔀
	General	System
	System	Motherboard Processor Acceleration
	Display	Processor(s):
\bigcirc	Storage	1 CPU 4 CPUs
	Audio	1% 100%
₽	Network	Extended Features: 💟 Enable PAE/NX
	Serial Ports	
Ø	USB	
	Shared Folders	
	User Interface	
		Invalid settings detected 🕅 🕅 Cancel

Fig. 24. Oracle VM VirtualBox Manager - settings

3. Afterwards restart the VM from the command line: run "*docker-machine start*".

serovyu@D02D11533590DIT \$ docker-machine start	MINGW64 /c/Program Files/Docker Toolbox
(default) Check network (default) Windows might	to re-create if needed ask for the permission to configure a dhcp server. Somet
imes, such confirmation	window is minimized in the taskbar.

Fig. 25. Run "docker-machine start"

4.7 eTrustEx WEB requirements

These are the current supported browsers and required settings for eTrustEx WEB:

Browser	Required	Additional information

Directorate-General for Informatics

ISA² Programme

Open e-PRIOR eInvoicing Integration with PEPPOL – Technical Specifications

0	Chrome	64	
	Firefox	59	Requires these 2 preferences to be enabled in about:config. — javascript.option.streams — dom.streams.enabled
9	Edge	17	This is the EdgeHTML version. Edge is only available in Windows 10



Configuring the platform

5 Configuring the platform

5.1 Use the existing default configuration

The system is preconfigured with the following parties:

- Supplier 'TRUSTSUPPARTY1', configured in the system with the identifier 'TRUSTSUPPARTY1' of type 'GLN'
- Customer 'TRUSTCUSTPARTY1', configured in the system with the identifier 'TRUSTCUSTPARTY1' of type 'GLN'

You will find the above identifiers in the sample SoapUI project which is part of the current release.

See chapter **<u>6.1 Using the provided SoapUI sample project</u>** for more details.

The platform uses the notion of 'third-party user' to identify the system sending documents to the platform on behalf of the Supplier and to identify the back-office system of the Customer. The third-party user is identified by a username and a password to be used in the HTTP basic authentication part when calling the web services exposed by the platform.

In this default configuration, the Supplier is linked with the third-party 'AS2ADAPTER' identified by:

- username 'AS2ADAPTER', with the password 'AS2ADAPTER'.

The Customer is linked with the third-party 'SP1_USER' identified by:

- username 'SP1_USER', with the password 'SP1_USER'.

The above usernames/passwords are already configured in the sample SoapUI project.

Additionally, interchange agreements for the mentioned above Supplier and Customer, and profiles 'Toolbox', 'eInvoicing', 'Bundle' are predefined in e-TrustEx.

To dispatch Bundle documents from e-TrustEx to e-TrustEx Web the Web Services Routing Endpoints configuration is added in e-TrustEx.

5.2 Create new configuration using the CIPAdmin module

The CIPAdmin web tool (in order to access it, please refer to the link in chapter <u>4.4</u> <u>Endpoints for accessing the applications of the platform</u>) is an admin console that allows provisioning the following:

• parties (Suppliers and Customers), including party identifiers

- interchange agreements: the technical link between the Supplier and Customer, authorizing them to exchange specific business documents with the platform
- routing endpoints (JMS or web services) for the back-office
- usernames (and corresponding passwords) to be used in the HTTP basic authentication when calling the web services of the platform

The user guide of this tool (*user_guide_cipa_adminconsole_open_etrustex.pdf*) is available here:

<u>https://joinup.ec.europa.eu/software/openetrustex/document/open-e-trustex-230-</u> <u>documentation</u>

5.3 Create new configuration for e-TrustEx Web module

The e-TrustEx Web module is configured at database level. The following elements can be managed:

- business configuration information,
- parties specify customer parties to which documents user can have granted access,
- users configure new users, grant roles, assign parties or business to which documents user can have access.

The user guide "e-TrustEx Web - Wildfly installation and configuration.doc" of this tool is available <u>here</u>.

Please refer to the chapter "3 WEB DATABASE CONFIGURATION" of the mentioned document.



Sending business messages to the platform

6 <u>Sending business messages to the platform</u>

There are two options available for the implementer to test the platform. They are described below.

The platform assumes that the Supplier and Customer used in the sample calls are already configured. See chapter <u>5. Configuring the platform</u> for more details on party configuration.

6.1 Using the provided SoapUI sample project

The release contains a sample SoapUI project (https://joinup.ec.europa.eu/svn/openeprior/branches/V_2_1_0_POST_AWARD/Tests/SoapUI/e Invoicing-2-1-soapui-project.xml) that allows calling the web services exposed by the platform. The project uses the preconfigured Sender/Receiver parties mentioned above in section **5.1 Use the existing default configuration**

It can be used to simulate both the Supplier and the Customer used in the e-Invoicing context.

6.1.1 As Supplier

For the Sender (Supplier) side it allows sending Invoices/CreditNotes and AttachedDocuments linked to them using the submitInvoice, submitCreditNote and submitAttachedDocument steps in the SoapUI project.

6.1.2 As Customer

For the Receiver (Customer) side, it allows to call the following services to consume the messages received from the Supplier:

submitInboxRequest: returns all the messages received by the Customer and not yet marked as 'Retrieved' after consuming them in the Customer's back-office. Once a message is consumed by the back-office, it should be marked as 'Retrieved' in the system, meaning that the next call to SubmitInboxRequest will not return this message anymore. In order to mark a message as 'Retrieved', the implementer of this solution should call the RetrieveRequest service with the RetrieveIndicator set to 'true' in the SOAP request, as shown in Fig. 26 below.

Open e-PRIOR elnvoicing Integration with PEPPOL – Technical Specifications

AP Reque	st 1 🚏 Request 1 🚏 for AttachedDocument
+= å	🕼 🖸 🗖 👬 🛢 🔒 http://192.168.99.100:8080/etrustex/services
Outline Raw XML	OAP-ENV:Envelope xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/"> <soap-env:header> <header xmlns="ec:services:wsdl:RetrieveRequest-2"></header></soap-env:header>
Eom	
	<pre><ns14:senderparty></ns14:senderparty></pre>
	<pre><ns14:receiverparty></ns14:receiverparty></pre>
Ξ	<pre><ns0:documentreferencerequest></ns0:documentreferencerequest></pre>
	<pre></pre>
</th <td> SOAP-ENV:Envelope></td>	 SOAP-ENV:Envelope>

Fig. 26. Mark document as Retrieved

- **submitRetrieveRequest**: it should be called for each business document returned by the InboxRequest service.
 - If it is called for an Invoice/CreditNote, it returns the UBL XML of the business document.
 - If it is called for an AttachedDocument it returns (in a HTTP multipart/related message) both the UBL XML of the AttachedDocument and the binary content of the AttachedDocument. Details below (Fig. 27) in a sample SoapUI response message:

Open e-PRIOR eInvoicing Integration with PEPPOL – Technical Specifications



Fig. 27. RetrieveRequest for AttachedDocument

- **submitViewRequest**: it allows to obtain the PDF human-readable representation produced by the system for each Invoice or CreditNote received. The PDF is returned as base64-encoded binary in the SOAP response message.
- submitApplicationResponse: it is used to inform e-PRIOR about the result of processing the Invoice/CreditNote in the back-office. The payload of this SOAP request is an UBL XML message.

6.2 Using the standalone client that simulates a sending Oxalis AccessPoint

It is important to note that the standalone client can only be used with a valid PEPPOL certificate. The default version included in this release uses a self-signed certificate, that must be replaced with a valid PEPPOL certificate obtained by the implementer of this solution.

6.2.1 Replacing the self-signed certificate with a valid PEPPOL certificate

So before being able to send any test message with this standalone client, the implementer of this solution should first obtain a valid PEPPOL certificate.

To obtain a valid PEPPOL certificate, follow the instructions provided in the chapter <u>2.1</u> <u>Obtaining a PEPPOL certificate for the AccessPoint.</u>

6.2.2 Configuring the standalone client

- Copy on your local drive the standalone client folder from the joinup SVN (https://joinup.ec.europa.eu/svn/openeprior/branches/V_2_1_0_POST_AWARD/Tests/stan dalone-client).
- 2. Once the certificate has been obtained and imported into a keystore file (keystore file should be named *oxalis-keystore.jks*), you should use it to override the default keystore file bundled in the client folder.

📁 Password

The default client configuration assumes that the password of the keystore is 'peppol'.

If a different password is selected, it should be set in the configuration settings, as explained below.

- **3.** The following variables should be updated in the file *oxalis-global.properties*:
 - **oxalis.keystore** must contain the path where the client has been stored on the local host
 - **oxalis.keystore.password** contains the keystore password (if not the default one 'peppol')
 - **oxalis.inbound.log.config** and oxalis.app.log.config must contain the path where the client has been stored on the local host (pointing to logback-oxalis.xml)
 - **oxalis.operation.mode** contains TEST or PRODUCTION, depending on the certificate type.
- **4.** Set the system variable OXALIS_HOME containing the path where the client has been stored on the local host.

6.2.3 Sample business messages provided in the package

This package contains two sample business documents (using UBL 2.1 syntax) for Invoice (https://joinup.ec.europa.eu/svn/openeprior/branches/V_2_1_0_POST_AWARD/Tests/standalo ne-client/BII04_v2_invoice1.xml) and CreditNote

(https://joinup.ec.europa.eu/svn/openeprior/branches/V_2_1_0_POST_AWARD/Tests/standalo ne-client/CreditNote_PEPPOL_BIS_att.xml), both having embedded attached documents.

Please note that each request (Invoice/CreditNote) sent to the platform must contain a unique document ID for the specific Supplier/Customer pair used in the message.

The unique key imposed by the system is made up of: documentID + documentType (Invoice or CreditNote) + Sender (Supplier) + Receiver (Customer).

So in order to respect this unique key, the above sample files must be updated with unique IDs per request (Invoice/cbc:ID or CreditNote/cbc:ID).

6.2.4 Instructions on how to send messages to the Oxalis AccessPoint

Below is an example for running the client for sending a test message to the Oxalis AccessPoint included in this package:

java -Dmail.mime.foldtext=false -Doxalis.transmissionbuilder.override=true -jar oxalisstandalone.jar -f "C:/conf/oxalis/BIIO4_v2_invoice1.xml" -u http://localhost:8081/oxalis/as2 m as2 -id APP_DIGIT_TEST -r 0088:TRUSTCUSTPARTY1 -s 0088:TRUSTSUPPARTY1

The parameters have the following meaning:

- '-f' specifies the absolute path to the test XML file. The path should be updated to your local path where the standalone client has been stored
- '-u' is the URL of the Oxalis AccessPoint instance
- '-id' specifies the identifier of the AccessPoint in the PEPPOL network. This value is the CN value from the PEPPOL certificate mentioned in chapter <u>5.2.1 Replacing</u> <u>the self-signed certificate with a valid PEPPOL certificate</u>. The current value used in this sample call (APP_DIGIT_TEST) is the CN value from the self-signed certificate provided by default in the client. As already mentioned, the self-signed certificate is to be replaced with a real PEPPOL certificate and its CN value should be used in the above call to the standalone client
- '-s' is the identifier of the Sender in the format schemeID:value
- '-r' is the identifier of the Receiver in the format schemeID:value
- The Sender and Receiver used in this call are the default Supplier/Customer described in chapter <u>5.1 Use the existing default configuration</u>

6.3 Checking the result of message processing in e-TrustEx

Once a message has been processed by the platform, the user can see the result of this process (document status, XML content, PDF human readable representation) either by querying the e-TrustEx database schema or by using the provided SoapUI project mentioned above.

6.3.1 Using the database

Follow the instructions in chapter **<u>4.6 Connecting to the database</u>**

Once connected you can run the following queries on the e-TrustEx schema:

- select * from etrustex.etr_tb_message where msg_document_id = 'AAA'; 'AAA' to be replaced with the actual document ID used in the sample XML message (value set in Invoice/cbc:ID or CreditNote/cbc:ID).
- select * from etrustex.etr_tb_message_binary where msg_bin_msg_id = MSG_ID;

Replace the MSG_ID parameter with the msg_id returned by the previous query.

In the result list of this query, the entry having msg_bin_type = 'RAW_MESSAGE' contains in the BLOB column 'msg_bin_file' the XML content of the business document sent by the supplier.

The entry having msg_bin_type = 'HUMAN_READABLE_MESSAGE' contains in the BLOB column 'msg_bin_file' the PDF human readable representation automatically generated by e-TrustEx for the Invoice and CreditNote.

6.3.2 Using SoapUl

The above mentioned sample SoapUI project can also be used to check the result of message processing in e-TrustEx.

The **'retrieveRequestBinding'** step can be used to call the RetrieveRequest service to obtain the XML content of the business document (Invoice or CreditNote) sent by the Supplier. If this service is called for an AttachedDocument, it returns both the XML and the binary content of the attachment.

The **'viewRequestBinding'** step can be used to call the ViewRequest service to obtain the PDF human-readable representation produced by e-TrustEx for each Invoice or CreditNote received. The PDF is returned as base64-encoded binary in the SOAP response message.

6.4 Business validation (Schematron)

The e-TrustEx component does a set of validations when receiving the business message for processing.

One of these validations is a business-rules validation implemented with the Schematron framework.

The current release uses the Schematron files released under PEPPOL Post-Award Business Interoperability Specifications (BIS), version BIS2.0-VA-V3.3.0. More details can be found here: <u>https://peppol.eu/downloads/post-award/</u>



Annex: Creating a customer e-Invoicing back-office

7 Annex : Creating a customer e-Invoicing back-office

This chapter describes the two integration patterns offered by e-TrustEx for Customers willing to connect their e-Invoicing back-office to consume the business messages received from Suppliers. It explains how the messages received in e-TrustEx from the Suppliers can be consumed and how the status updates can be submitted to e-TrustEx once the back-office has consumed the business documents.

The term e-PRIOR used in the diagrams below refers to the eProcurement-related services exposed by the more generic e-TrustEx platform used in this package.

\rm IMPORTANT NOTICE

The current package does not include any default Customer back-office implementation.

The information below provides guidance on the two options available for plugging a backoffice system to the platform.

7.1 Store and Forward messaging pattern

This pattern is a mix of JMS and web services usage. It is described in the diagram below.



Fig. 28. Store&Forward integration pattern

e-PRIOR is forwarding the business messages to a JMS queue in the customer's back-office.

In order to configure a JMS queue where the messages will be routed to, please refer to the CIPAdmin user guide, in chapter **5.2 Create new configuration using the CIPAdmin module**.

What is sent over JMS:

- the business documents metadata (UBL XML of Invoice and CreditNote)
- the metadata of AttachedDocuments (UBL XML). Not the binary content of the attachment.

For each invoice and credit note received from the suppliers, e-PRIOR generates a human readable version in PDF format. The binary content of the attachedDocuments sent by the supplier is also stored in e-PRIOR. Back-office systems can obtain both the human readable and the attachments' binary content by calling web services exposed by ePrior.

The customer system will have to call web services for the following:

- for each AttachedDocument XML received in the queue, call the RetrieveRequest service to obtain the binary content
- for each Invoice and CreditNote received in the queue, call the ViewRequest service to obtain the PDF human readable.
- once the processing of the invoice/creditNote has been done in the back-office, call the SubmitApplicationResponse service to update the status (ACCEPTED/REJECTED) of the business document

7.2 Store and Collect messaging pattern

This pattern uses only web services to pull information from e-PRIOR and to push status updates. It is described in the diagram below.

Open e-PRIOR eInvoicing Integration with PEPPOL – Technical Specifications



Fig. 29. Store&Collect integration pattern

The central point in this integration pattern is the Inbox concept used by e-PRIOR to store documents received by a specific party. In the context of this document, the Inbox stores the elnvoicing documents received by the customers.

When calling the InboxRequest service, the customer back-office receives the most recent 500 documents (Invoice/CreditNotes and their related AttachedDocuments) created in e-PRIOR for that customer and not yet marked as 'Retrieved' by the customer.

When processing the InboxResponse SOAP message, the customer system will have to:

- for each Invoice and CreditNote received, call the RetrieveRequest service to get the XML of the business document
- for each AttachedDocument found in the InboxResponse, call the RetrieveRequest service to get the XML metadata and the binary content

Once the processing of the Invoice/CreditNote has been done in the back-office, the next actions are mandatory:

- call the SubmitApplicationResponse service to update the status (ACCEPTED/REJECTED) of the business document
- call the RetrieveRequest service to mark the document as 'Retrieved' in e-PRIOR, in order to not appear anymore in the next calls to InboxRequest. This is an important aspect, linked to the limitation of 500 documents in the response, mentioned above. If the back-office does not mark documents as 'Retrieved' they will pile-up in e-PRIOR and once the limit of 500 documents is reached, the oldest ones will be ignored, so not returned in the InboxResponse.

7.3 Description of the web services

The web services exposed by e-TrustEx are SOAP based web services, using HTTP Basic Authentication.

The WSDLs of the web services are below:

- http://localhost:8080/eprior/wsdl/Invoice-2.1.wsdl
- <u>http://localhost:8080/eprior/wsdl/CreditNote-2.1.wsdl</u>
- <u>http://localhost:8080/etrustex/wsdl/AttachedDocument-2.0.wsdl</u>
- <u>http://localhost:8080/etrustex/wsdl/InboxRequest-2.0.wsdl</u>
- http://localhost:8080/etrustex/wsdl/RetrieveRequest-2.0.wsdl
- http://localhost:8080/etrustex/wsdl/ViewRequest-2.0.wsdl
- <u>http://localhost:8080/etrustex/wsdl/ApplicationResponse-2.0.wsdl</u>
- <u>http://localhost:8080/etrustex/wsdl/DocumentWrapper-2.0.wsdl</u>
- <u>http://localhost:8080/etrustex/wsdl/DocumentBundle-2.0.wsdl</u>

In case of DockerToolbox, please refer to chapter <u>4.5 Specific settings when running</u> <u>Docker Toolbox on Windows or Mac</u>, to replace 'localhost' in the URLs above with the real IP address of the docker-machine running on your computer.

SubmitInboxRequest: returns all the messages received by the Customer and not yet marked as 'Retrieved' after consuming them in the Customer's back-office. Once a message is consumed by the back-office, it should be marked as 'Retrieved' in the system, meaning that the next call to SubmitInboxRequest will not return this message anymore. In order to mark a message as 'Retrieved', the implementer of this solution should call the RetrieveRequest service with the RetrieveIndicator set to 'true' in the SOAP request.

SubmitRetrieveRequest: it should be called for each business document returned by the InboxRequest service (in the Store and Collect pattern) and for each AttachedDocument received in the JMS queue (in the Store and Forward pattern).

- If it is called for an Invoice/CreditNote, it returns the UBL XML of the business document.
- If it is called for an AttachedDocument it returns (in a HTTP multipart/related message) both the UBL XML of the AttachedDocument and the binary content of the AttachedDocument.

SubmitViewRequest: it allows obtaining the PDF human-readable representation produced by e-PRIOR for each Invoice or CreditNote received. The PDF is returned as base64-encoded binary in the SOAP response message.

SubmitApplicationResponse: it is used to inform e-PRIOR about the result of processing the Invoice/CreditNote in the back-office. The payload of this SOAP request is an UBL XML message.

The response can be either ACCEPT or REJECT. To differentiate between the two types, the ResponseCode element in the payload is used, with the following possible values:

- '380:1' for Invoice ACCEPTED
- '380:2' for Invoice REJECTED
- '81:1' for CreditNote ACCEPTED
- '81:2' for CreditNote REJECTED
- '916:1' for AttachedDocument ACCEPTED
- '916:2' for AttachedDocument REJECTED

The SoapUI project provided in this release (*6.1 Using the provided SoapUI sample project*) contains two sample request messages for ACCEPTED/REJECTED.